

Siemens PLM Software 技術技巧及新聞

歡迎流覽《Siemens PLM Software 技術技巧及新聞》，希望它能成為 Siemens PLM Software 技術支援團隊將 Siemens PLM Software 最新產品更新、技術技巧及新聞傳遞給用戶的一種途徑


Date: 2015/05/15

NX Tips

1. 如何設置裝配導航器預設顯示為 Pack 或者 Unpack 狀態

通過下面步驟可以調整 pack/unpack 預設設置:

File→utilities→customer Defaults→gateway→assembly navigator→all→pack components



在你打開裝配的時候，這個選項控制了裝配導航器中相同的零件是否被打包顯示。

Teamcenter Tips

2. 如何指派 pool manager 到一個特定 IP 位址？

在具有多個網卡的伺服器上，池伺服器 GMS 位址可以配置到你想要使用的網卡上。

通過修改下面三個檔，硬編碼 GMS 位址來實現

以 TC10 為例：

%TC_ROOT%\pool_manager\confs\config1\serverPool.properties SERVER_HOST=10.0.1.222

```
# By default, CORBA will determine the IP address for use in IORs used
# to connect to the servers. On a machine with multiple IP addresses
# it sometimes makes a poor choice. Set this parameter to a logical
# host name to override an inappropriate choice. Leave it unset
# to get the default behavior.
SERVER_HOST=10.0.1.222
```

%TC_ROOT%\pool_manager\confs\config1\TreeCacheTCP.xml

Add bind_addr value <attribute name="ClusterConfig"> <config> <TCP bind_addr="10.0.1.222" start_port="17800".....

```
-->
<attribute name="ClusterConfig">
  <config>
    <TCP bind_addr="10.0.1.222" start_port="17800" end_port="17800" sock_conn_timeout="2000" use_send_queues="fa
    <TCPPING initial_hosts="cnbjhwin7[17810]" port_range="1" timeout="15000" num_initial_members="1" up_thread=
    <MERGE2 min_interval="5000" max_interval="10000" />
    <FD SOCK />
```

2015-5-22

%TC_ROOT%\pool_manager\confs\config1\etc\jacord.properties

OAIAddr=10.0.1.222

```
#
#####


# IP address on multi-homed host (this gets encoded in
# object references). NOTE: Addresses like 127.0.0.X
# will only be accessible from the same machine!
OAIAddr=10.0.1.222
#OAPort=4711
```

GTAC Greater China

Solid Edge Tips

3. **Favorites Materials** 清單資訊存儲在什麼地方？

Solid Edge Material table 下面的資訊，包括 Favorite Materials lists 都存儲在 material library 檔中。



默認安裝環境，這些檔存放在 C:\Program Files\Solid Edge ST7\Preferences\Materials 當然，你也可以通過 Solid Edge Options → File Locations → Material Table 來指定 SE 讀取不同目錄下的材料表資訊。

Greater China

ME&S Service Team

PRC Helpdesk (Mandarin): 800-810-1970

Taiwan Helpdesk (Mandarin): 00801-86-1970

HK Helpdesk (Cantonese): 852-2230-3322

Helpdesk Email: helpdesk_cn.plm@siemens.com

Global Technical Access Center: <http://support.ugs.com>

Siemens PLM Software Web Site: <http://www.plm.automation.siemens.com>

Siemens PLM Software (China) Web Site: http://www.plm.automation.siemens.com/zh_cn/

此e-mail newsletter 僅提供給享有產品支援與維護的Siemens PLM 軟體使用者。當您發現問題或希望棄訂，請發送郵件至 helpdesk_cn.plm@siemens.com 聯繫，如棄訂，請在標題列中注明“棄訂”