

Siemens PLM Software 技術技巧及新聞

歡迎流覽《Siemens PLM Software 技術技巧及新聞》，希望它能成為 Siemens PLM Software 技術支援團隊將 Siemens PLM Software 最新產品更新、技術技巧及新聞傳遞給用戶的一種途徑

Date: 2015/01/23

NX Tips

1. Java 一直報錯 “Allow access to the following application...”

問題/症狀

當我啟動 NX help 的時候一直出現錯誤：

Security Warning

Allow access to the following application from this web site?

Web Site: file://

Application: UNKNOWN

Publisher: UNKNOWN

This web site is requesting access and control of the java application shown above.

Allow access only if you trust the web site and know that the application is intended to run on this site.

[] Do not show this again for this app and website. [Allow] [Do Not Allow]


即使我選擇了上面的不再顯示這個錯誤，還是不斷有這個警告出現。

解決方法

您需要使 Java Caching 可用，按下面的做法：


開始à控制台à 找到“java”

在 General 頁上的 "Temporary Internet Files", 選擇 “setting”，



選擇 "Keep temporary files on my computer", 選擇 OK

如圖:



重新啟動瀏覽器就可以了。


2. 如何知道我使用的是第一視角投影還是第三視角投影？

問題/症狀

由於編輯“圖紙頁”無法看到是第一視角還是第三視角，我怎樣用簡單的方式看出？

解決方法

編輯“圖紙頁”中是不顯示第一視角還是第三視角的，最方便的方法是這樣做：


選擇：信息  圖紙

然後會得到如下的資訊：

正投影角 第一

或者

正投影角 第三



Teamcenter Tips

3. 如何限制拖拽功能來創建特定的資料集類型

使用者不希望在業務物件，比如零元件版本下通過拖拽功能創建特定的資料集，希望限制該功能。

下面是一個例子來展示如何對 **TIF** 資料集類型進行限制。

請執行下面的步驟來限制零元件版本下通過拖拽創建 **TIF** 資料集類型

1. 打開 **BMIDE**
2. 在業務物件零元件版本先增加下面的 **GRM** 規則


Primary Object = ItemRevision
Secondary Object = TIF
Relation Object = IMAN_specification
Primary Cardinality = 0
Secondary Cardinality = 0
Changeability = Changeable
Attachability = Unrestricted
Detachability = Unrestricted

The screenshot shows the 'Modify GRM Rule' dialog box. The title bar says 'Modify GRM Rule'. Inside, there's a section 'GRM Rule' with the subtitle 'Modify a GRM rule'. Below this, there are fields for 'Project' (set to 'Helpdesk'), 'Primary Object' (set to 'ItemRevision'), 'Secondary Object' (set to 'TIF'), and 'Relation Object' (set to 'IMAN_specification'). Each object field has a 'Browse...' button. Below these, there are fields for 'Primary Cardinality' (set to 0), 'Secondary Cardinality' (set to 0), 'Changeability' (set to 'Changeable'), 'Attachability' (set to 'Unrestricted'), and 'Detachability' (set to 'Unrestricted'). At the bottom right, there are 'Finish' and 'Cancel' buttons. A watermark 'GTAC Greater China' is visible in the bottom right corner of the image.

3. 保存並部署 **BMIDE**

2015-1-23


4. 在首選項 DRAG_AND_DROP_default_dataset_type 中增加格式為
DRAG_AND_DROP_default_dataset_type 的值：tif:TIF



5. 關閉 TC
6. 打開一個新的 TC 會話，拖拽 TIF 資料集



在點擊 OK 按鈕後，TC 會彈出錯誤對話方塊



Greater China
ME&S Service Team
PRC Helpdesk (Mandarin): 800-810-1970
Taiwan Helpdesk (Mandarin): 00801-86-1970
HK Helpdesk (Cantonese): 852-2230-3322
Helpdesk Email: helpdesk_cn.plm@siemens.com
Global Technical Access Center: <http://support.ugs.com>
Siemens PLM Software Web Site: <http://www.plm.automation.siemens.com>
Siemens PLM Software (China) Web Site: http://www.plm.automation.siemens.com/zh_cn/

此e-mail newsletter 僅提供給享有產品支援與維護的Siemens PLM 軟體使用者。當您發現問題或希望棄訂，請發送郵件至 helpdesk_cn.plm@siemens.com 聯繫，如棄訂，請在標題列中注明“棄訂”